

eBook Mobile for Nokia S60

User Guide

Document
Version 1.0

1 Features

eBook Mobile is a handy eBook Reader for your phone, you can read your favourite ebooks in pure PDB,PRC or TXT format.

It features:

- Support English, Traditional Chinese, Simplified Chinese and Unicode (UTF-8) eBook documents
- Auto-search all ebooks in Inbox(including My Folders/Hot Messages)/Phone memory/Memory card
- Inbox's eBook files can be copied to other folder location
- Enable Portrait/Landscape Full/Standard screen view mode
- Bookmark
- Text search
- Toggle Font size
- Selectable Foreground font color/Background color/Highlighted color (used in Search)
- Backlight support
- Rename/Delete eBook filename

2 System Requirements

To install and run eBook Mobile, you need the following:

- Nokia S60 phone or compatibles running Symbian 7.0s/8.x: e.g. Nokia N70/6680/6681/6682/6630/6600/6620/7610/6670/6260/3230/Panasonic X700/X800; minimum 300k storage, 400k free memory to run
- Bluetooth/IR/Cable between your PC and the phone
- A PC desktop with PC Suite 6.5 or above for phone installed on Windows 2000/XP (If you are using Nokia 6600, please install PC Suite for Nokia 6600)

3 Installation


3.1 Using PC Suite

- a) Download the trial/full installation file to your desktop PC
- b) Unzip the zip file and run the installation .sis file for your preferred language:


eBookMobileV2_NS60_201_EN.SIS English full version

eBookMobileV2_NS60_201_Trial_EN.SIS English trial version


- c) Connect your phone to the PC using Bluetooth/Infra-Red/Cable (please refer to your phone manual)
- d) Start PC Suite and choose "Install Applications" icon




e) On the left-side pane, choose the appropriate sis file and drag-and-drop to the right-side pane. The sis file will be sent to your phone and start installation



f) During the installation process, your phone will prompt "Application is untrusted...." you can ignore this warning message and press "Yes" to continue



g) Choose the storage location (Phone/Memory Card) to install the program, "Memory Card" is preferred to save main phone memory



h) Another "Please read..." screen displays the license agreement. Please read through it and if you accept it then press "Yes" to proceed with the installation OR click "No" to abort the installation




i) If it is the first time to run the full version, registration code is required to enter once. (You will need to provide your phone's IMEI to us to get the registration code, your phone IMEI can be shown by pressing *#06#)



Enter registration code:

OK Cancel

j) After the installation has completed, press the Application Launch button to locate the program icon to run (For N70, the program will be installed in "My Own" folder)




Note:

Your registration code is given based on the IMEI (a 15-digit unique serial number on the GSM phone) on your phone. You have to supply the IMEI to m-internet to generate the registration code. IMEI will be shown by pressing *#06# on your phone keypad, write it down and send it via email to support@m-internet.com for assistance. Make sure you can install each copy in one device only!!

3.2 Using Infra-Red/Bluetooth/Cable Connection

Alternatively, you can directly "beam" the installation sis file to your phone via Infra-Red/Bluetooth or Cable. It will be stored as a New Message in the inbox of your phone.


Note: Some phones support Bluetooth connection only.



Open the New Message and the installation will start automatically and follow Section 3.1 step (f) onward.

4 Removing Program

Once installed, an entry called "**eBook Mobile**" will be listed in the Applications Manager program under the "Tools" folder. Select this entry and press Left-Soft-Key "Options->Remove" to remove the application.




5 How to use

5.1 How to store ebook files to the phone

You need to store your favourite ebook files to your phone before you can read it using **eBook Mobile**. You can do this in the following ways:


- *Copy files using PC Suite's File Manager*

After you have properly installed the PC Suite, you can run the "File Manager" in the PC Suite main menu or open your Windows' Explorer to see the contents inside your phone or memory card.





Then you can copy-&-paste your ebook files from your PC to either phone memory/memory card. Open **eBook Mobile** Storage tab and choose your destination folder storing ebook files.

Below figure shown the ebook files are copied to the memory card folder named “ebooks”.



- *Beam files from PC to your phone by Bluetooth/Infra-Red*


eBook Mobile has the capability to scan through your Message's Inbox for files of .txt/.prc/.pdb extension. You can simply send the ebook file to your phone from your PC to the phone by Bluetooth/Infra-Red, and click the “Inbox” tab in **eBook Mobile** as shown below.



- ***Copy files to external memory card using optional Memory Card Reader***



Or if you have external memory card and an optional memory card reader, you can connect the memory card to your PC with the memory card reader. After that you can put your ebook files to some location of the memory card and put it back to your phone. Open **eBook Mobile** Storage tab and choose your destination folder storing ebook files to read it.

5.2 Storage/Inbox/Bookmark Tab

In the Application menu, navigate to the icon  and press navigation button to start the program.



There are 3 tabs on the top: **Bookmark/Storage/Inbox**:



Bookmark:

This tab page view shows all the saved bookmarks associated with opened book.

The first level is the book name and 2nd level is the saved bookmark name added by key [*]

Storage:

Directory structure showing “Phone” and “Memory Card” as the root objects. You can use this tab to browse to your folder containing ebook files and open it.


Inbox:

eBook Mobile can scan your Message Inbox (including My Folders/Hot Messages folders) and you can directly open that ebook file in this tab.


5.3 Functions

On Tab view window:

If you are in the tab view window (Bookmark/Storage/Inbox), you can press LSK(Left-Soft-Key) to have a basic menu:




The most common use is Settings -> Default Doc. Encoding: (English/Traditional Chinese (Big5)/Simplified Chinese (GB2312)). User can configure this global language setting to apply for all opened ebook files.



Or you can specifically configure individual document language setting after file opened and press LSK -> File -> Encoding.

On Open file window:

When you open an ebook, you can choose all functions using menu LSK:




or some defined shortcut-keys for the most common functions:

- [1] - Anti-Clockwise landscape mode/Normal view mode
- [2] - Full screen/Normal view mode
- [3] - Clockwise landscape mode/Normal view mode
- [4] - Previous Bookmark
- [5] - Toggle font size (large/small)
- [4] - Next Bookmark
- [8] - Search Next
- [0] - Search

- [#] - File properties (Full pathname/Date created/File size/Timestamp)
- [*] - Add Bookmark
- [C] - Delete Bookmark

Display:

You can toggle your document view in normal (partial) or full screen mode. Also to have a better view, **eBook Mobile** supports +90/-90 degrees Landscape/ Portrait view.



File:

File properties show the document's Full pathname/Date created/File size/Timestamp; Encoding sets for English/Traditional Chinese (Big5)/Simplified Chinese (GB2312)/UTF-8.



Settings:

Default Doc. Encoding:

(English/Traditional Chinese (Big5)/Simplified Chinese (GB2312)).
User can configure this global language setting to apply for all opened ebook files.

Font Size:

Toggle large/small font size.

Backlight:

Enable backlight always on or based on the phone setting. "Always on" should be used in caution because it will drive your battery drain.

Font Colour:


The text colour.

Background Colour:

Background colour of the opened ebook document.

Highlight Colour:


Used in Search function. The searched string will be shown in this preset colour.



Bookmark:

Add:

Add the bookmark in the current top position, also you can name this bookmark and it will be shown in the Bookmark tab view.




Delete:

Delete the current bookmark.

Browse:


You can go to "First page"/"Last page" or go to previous/next Bookmark.



Search:

Enter the search string to search for specific word. The search string will be displayed in Highlighted colour defined in Settings.

Press key [8] again to advance to the next search result.



aren't even there yet."

"I will be fine when we land," he said, as firmly as a shattered person could manage. "By the way, **Eva**, nice bedside manner. I think you missed your calling. You should've gone into nursing."

"Shut up," I answered, and closed my eyes again to calm my stomach.

"Both of you shut up." Eileen yawned. "I told you your

6 Contact, Support and Questions

Please regularly visit website <http://m-internet.com> for further update.

Email Enquiry:

General Information:	info@m-internet.com
Support:	support@m-internet.com
Sales:	sales@m-internet.com

7 Copyright

Other products may be trademarks or registered trademarks of their respective manufacturers.

(c) 2005-2006 m-internet.com Limited. All rights reserved.

m-internet.com Ltd. operates a policy of continuous improvement. Therefore we reserve the right to make changes and improvements to any of the products described in this guide without prior notice.

m-internet.com Ltd. is not responsible for any loss of data, outcome or any consequential damage howsoever caused.